FREE CROCHET PATTERN

Heart Mug Cozy

Tapestry crochet band of three hearts · 9.25 × 3.56 in · button strap · US terms

SKILL LEVEL	SIZE	HOOK
Easy+	9.25 × 3.56 in	4.5 mm (US 7)
YARN	**GAUGE**	**TIME**
Worsted (#4) cotton	4 sc × 4.5 rows = 1 in	About 2 hours

Materials

- Worsted (#4) cotton: cream (MC) about 26 yd, red (CC) about 13 yd
- 4.5 mm (US 7) hook, tapestry needle, one 3/4 in (19 mm) button

Abbreviations (US terms)

ch	chain	**CC**	contrast colour (red)
sc	single crochet	**RS / WS**	right side / wrong side
MC	main colour (cream)	**st(s)**	stitch(es)

Colour change: work the last sc before the change until 2 loops are left on the hook, then pull through with the new colour. Carry the unused colour along the top of the row below and crochet over it so it's hidden. Odd rows are RS rows.

Cozy

Foundation	With MC (cream), ch 38.	
Row 1 (RS)	Sc in the 2nd ch from the hook and in each ch across. Turn.	**(37)**
Rows 2–5	Ch 1, sc in each st across with MC. Turn.	**(37)**

Heart band: join CC in Row 6. Carry the colour you're not using along the top of the row below and work over it.

Row 6 (WS)	Ch 1, MC 7, CC 1, MC 10, CC 1, MC 10, CC 1, MC 7. Turn.	**(37)**
Row 7 (RS)	Ch 1, MC 6, CC 3, MC 8, CC 3, MC 8, CC 3, MC 6. Turn.	**(37)**
Row 8 (WS)	Ch 1, MC 5, CC 5, MC 6, CC 5, MC 6, CC 5, MC 5. Turn.	**(37)**
Row 9 (RS)	Ch 1, MC 4, CC 7, MC 4, CC 7, MC 4, CC 7, MC 4. Turn.	**(37)**
Row 10 (WS)	Ch 1, MC 4, CC 7, MC 4, CC 7, MC 4, CC 7, MC 4. Turn.	**(37)**
Row 11 (RS)	Ch 1, MC 5, CC 2, MC 1, CC 2, MC 6, CC 2, MC 1, CC 2, MC 6, CC 2, MC 1, CC 2, MC 5. Turn.	**(37)**
Rows 12–16	Cut CC. Ch 1, sc in each st across with MC. Turn. Fasten off after Row 16.	**(37)**

Border

Round	With CC, join in any corner. Ch 1, sc evenly around: 1 sc in each st along the top and bottom, 1 sc in each row end along the sides, 3 sc in each corner. Sl st to the first sc.	**(114)**

Strap

Rows 1–8	With CC, join to one short edge at Row 7. Ch 1, work 4 sc along the row ends (Rows 7–10). Turn. Ch 1, sc in each st across for 8 rows.	**(4)**
Row 9	Ch 1, sc in the first st, ch 2, skip 2 sts, sc in the last st (buttonhole). Fasten off.	
Button	Sew the button to the other short edge, level with the strap. Wrap the cozy round the mug with the handle in the gap and button it.	

Heart Mug Cozy · Colour Chart

37 sts × 16 rows of sc. Each square = 1 sc. Odd (RS) rows read right to left, even (WS) rows left to right.



Finished: 9.25 × 3.56 in (23.5 × 9.0 cm) before the border · fits a 10–11 in (25–28 cm) mug, handle in the gap

Red border: 114 sc (3 sc in each corner) · strap: 4 sc × 8 rows + buttonhole row

Yarn: cream (MC) 26 yd, red (CC) 13 yd · carry the unused colour inside the stitches

cozymakery.com